

Package ‘geonapi’

January 20, 2020

Type Package

Title 'GeoNetwork' API R Interface

Version 0.3-1

Date 2020-01-20

Maintainer Emmanuel Blondel <emmanuel.blondel1@gmail.com>

Description Provides an R interface to the 'GeoNetwork' API (<<https://geonetwork-opensource.org/#api>>) allowing to upload and publish metadata in a 'GeoNetwork' web-application and expose it to OGC CSW.

Depends R (>= 3.1.0), geometa

Imports R6, openssl, httr, XML

Suggests testthat, roxygen2

License MIT + file LICENSE

URL <https://github.com/eblondel/geonapi/wiki>,
<https://geonetwork-opensource.org>

BugReports <https://github.com/eblondel/geonapi/issues>

LazyLoad yes

RoxygenNote 6.1.1

NeedsCompilation no

Author Emmanuel Blondel [aut, cre] (<<https://orcid.org/0000-0002-5870-5762>>)

Repository CRAN

Date/Publication 2020-01-20 17:00:17 UTC

R topics documented:

geonapi	2
GNManager	2
GNPrivConfiguration	4
GNRESTRequest	5
GNUtills	6
GNVersion	7

Index **9**

geonapi *'GeoNetwork' API R Interface*

Description

Provides an R interface to the 'GeoNetwork' API (<<https://geonetwork-opensource.org/#api>>) allowing to upload and publish metadata in a 'GeoNetwork' web-application and expose it to OGC CSW Web-Services (Catalogue Service for the Web).

Details

Package: geonapi
 Type: Package
 Version: 0.3-1
 Date: 2020-01-20
 License: MIT
 LazyLoad: yes

Author(s)

Emmanuel Blondel <emmanuel.blondel1@gmail.com>

GNManager *GeoNetwork REST API Manager*

Description

GeoNetwork REST API Manager

Usage

GNManager

Format

[R6Class](#) object.

Value

Object of [R6Class](#) with methods for communication with the REST API of a GeoNetwork instance.

Fields

loggerType the type of logger
 verbose.info if geosapi logs have to be printed
 verbose.debug if curl logs have to be printed
 url the Base url of GeoNetwork
 version the version of GeoNetwork. Handled as GNVersion object
 user the user name

Methods

new(url, user, pwd, version, logger) This method is used to instantiate a GNManager with the url of the GeoNetwork and credentials to authenticate (user/pwd). By default, the logger argument will be set to NULL (no logger). This argument accepts two possible values: INFO: to print only geonapi logs, DEBUG: to print geonapi and CURL logs

logger(type, text) Basic logger to report geonapi logs. Used internally

INFO(text) Logger to report information. Used internally

WARN(text) Logger to report warnings. Used internally

ERROR(text) Logger to report errors. Used internally

getUrl() Get the authentication URL

getLang() Get the service lang

login(user, pwd) This methods attempts a connection to GeoNetwork REST API. User internally during initialization of GNManager.

getClassName() Retrieves the name of the class instance

insertMetadata(xml, file, geometa, group, category, stylesheet, validate, geometa_validate, geometa_ins) Inserts a metadata by file, XML object or **geometa** object of class ISOMetadata or ISOFeatureCatalogue. If successful, returns the Geonetwork metadata internal identifier (integer). Extra parameters geometa_validate (TRUE by default) and geometa_inspire (FALSE by default) can be used with geometa objects for perform ISO and INSPIRE validation respectively.

setPrivConfiguration(id, config) Set the privilege configuration for a metadata. 'id' is the metadata integer id. 'config' is an object of class "GNPrivConfiguration".

get(id, by, output) Generic getter for metadata. Possible values for by are 'id', 'uuid'. Used internally only. The 'output' argument gives the type of output to return, with possible values "id", "metadata", "info".

getMetadataById(id) Get a metadata by Id. Returns an object of class ISOMetadata (ISO 19115) or ISOFeatureCatalogue (ISO 19110) (from **geometa** package)

getMetadataByUUID(uuid) Get a metadata by UUID. Returns an object of class ISOMetadata (ISO 19115) or ISOFeatureCatalogue (ISO 19110) (from **geometa** package)

getInfoById(id) Get a metadata Info by Id. Returns an XML document object

getInfoByUUID(uuid) Get a metadata Info by UUID. Returns an XML document object

updateMetadata(id, xml, file, geometa, geometa_validate, geometa_inspire) Updates a metadata by file, XML object or **geometa** object of class 'ISOMetadata' or 'ISOFeature-Catalogue'. Extra parameters geometa_validate (TRUE by default) and geometa_inspire (FALSE by default) can be used with geometa objects for perform ISO and INSPIRE validation respectively.

deleteMetadata(id) Deletes a metadata

deleteMetadataAll() Deletes all metadata for which the authenticated user is owner

Author(s)

Emmanuel Blondel <emmanuel.blondell@gmail.com>

Examples

```
## Not run:
  GManager$new("http://localhost:8080/geonetwork", "admin", "geonetwork")

## End(Not run)
```

GNPrivConfiguration *A GeoNetwork privilege configuration*

Description

This class is an utility to configure privileges

This class is an utility to configure privileges

Usage

GNPriv

GNPrivConfiguration

Format

[R6Class](#) object.

Details

GeoNetwork REST API - GeoNetwork privilege configuration

GeoNetwork REST API - GeoNetwork privilege configuration

Value

Object of [R6Class](#) for modelling a GeoNetwork Privilege configuration

Object of [R6Class](#) for modelling a GeoNetwork Privilege configuration

Methods

`new()` This method is used to instantiate a GNPriv object.

`new()` This method is used to instantiate a GNPrivConfiguration object.

`setPrivileges(group, privileges)` Sets the operation privileges for a particular group. Allowed group values are "guest", "intranet" and "all". Allowed values for operation privileges are "view", "download", "editing", "notify", "dynamic" and "featured".

Author(s)

Emmanuel Blondel <emmanuel.blondel1@gmail.com>

Emmanuel Blondel <emmanuel.blondel1@gmail.com>

Examples

```
## Not run:
priv <- GNPriv$new(group="all", privileges=c("view","dynamic","featured"))

## End(Not run)

## Not run:
pcfg <- GNPrivConfiguration$new()
pcfg$setPrivileges("all", c("view","dynamic","featured"))

## End(Not run)
```

GNRESTRequest

GeoNetwork REST API REST Request

Description

GeoNetwork REST API REST Request

Usage

```
GNRESTRequest
```

Format

[R6Class](#) object.

Value

Object of [R6Class](#) for modelling a GeoNetwork REST request

Abstract Methods

new() This method is used to instantiate a GNRESTRequest
 setChild(key,value) Sets a child element
 encode() Encodes a GNRESTRequest R6 object to XML representation

Author(s)

Emmanuel Blondel <emmanuel.blondel1@gmail.com>

GNUtils

GeoNetwork REST API Manager Utils

Description

GeoNetwork REST API Manager Utils

Usage

GNUtils

Format

[R6Class](#) object.

Value

Object of [R6Class](#) with static util methods for communication with the REST API of a GeoNetwork instance.

Static methods

getUserAgent() This method is used to get the user agent for performing GeoNetwork API requests. Here the user agent will be compound by geonapi package name and version.

getUserToken(user, pwd) This method is used to get the user authentication token for performing GeoNetwork API requests. Token is given a Base64 encoded string.

GET(url, path, token, verbose) This method performs a GET request for a given path to GeoNetwork REST API

PUT(url, path, token, filename, contentType, verbose) This method performs a PUT request for a given path to GeoNetwork REST API, to upload a file of name filename with given contentType

POST(url, path, token, content, contentType, verbose) This method performs a POST request for a given path to GeoNetwork REST API, to post content of given contentType

DELETE(url, path, token, verbose) This method performs a DELETE request for a given GeoNetwork resource identified by a path in GeoNetwork REST API

parseResponseXML(req) Convenience method to parse XML response from GeoNetwork REST API. Although package **httr** suggests the use of **xml2** package for handling XML, **geonapi** still relies on the package **XML**. Response from **httr** is retrieved as text, and then parsed as XML 'xmlParse' function.

getPayloadXML(obj) Convenience method to create payload XML to send to GeoNetwork.

Author(s)

Emmanuel Blondel <emmanuel.blondel1@gmail.com>

GNVersion

A GeoNetwork version

Description

This class is an utility wrap the Geonetwork version

Usage

GNVersion

Format

[R6Class](#) object.

Details

GeoNetwork REST API - GeoNetwork Version

Value

Object of [R6Class](#) for modelling a GeoNetwork version

Methods

new(version) This method is used to instantiate a GNVersion object.

lowerThan(version) Compares to a version and returns TRUE if it is lower, FALSE otherwise

greaterThan(version) Compares to a version and returns TRUE if it is greater, FALSE otherwise

equalTo(version) Compares to a version and returns TRUE if it is equal, FALSE otherwise

Author(s)

Emmanuel Blondel <emmanuel.blondel1@gmail.com>

Examples

```
## Not run:  
version <- GNVersion$new("2.6.4")  
  
## End(Not run)
```


Index

*Topic **GeoNetwork**

GNPrivConfiguration, 4

GNVersion, 7

*Topic **api**

GNManager, 2

GNRESTRequest, 5

GNUtils, 6

*Topic **configuration**

GNPrivConfiguration, 4

*Topic **geonetwork**

GNManager, 2

GNRESTRequest, 5

GNUtils, 6

*Topic **privilege**

GNPrivConfiguration, 4

*Topic **rest**

GNManager, 2

GNRESTRequest, 5

GNUtils, 6

*Topic **version**

GNVersion, 7

geonapi, 2

geonapi-package (geonapi), 2

GNManager, 2

GNPriv (GNPrivConfiguration), 4

GNPrivConfiguration, 4

GNRESTRequest, 5

GNUtils, 6

GNVersion, 7

R6Class, 2, 4–7